

POCKET LCARS for Wisbar Advance and Wisbar Advance Desktop

Revised 14 October 2007

PRIORITY ONE TRANSMISSION: Welcome to the 24th century! Because the 21st century has not yet seen the general release of the neural interface, it will be necessary for you to assimilate these instructions the old fashioned way: Read them. They will provide a wealth of knowledge and will guide you, step by step, through the installation process.

The **PADD**, commonly used by Starfleet personnel, strongly resembles the Pocket PC handheld devices of the early 21st century. As a forward-thinking citizen and Pocket PC owner from the 21st century, you want your device to reflect the future of which you'd like to be a part.



While we cannot offer you a visit to the bridge of the starship Enterprise (you'll have to [go to Las Vegas for that](#)), nor can we offer you multi-terahertz performance or giga-quads of storage space as an upgrade, we *can* offer you the experience of computing with a 24th century style interface.

That interface is **Pocket LCARS**.

Now you can experience **LCARS** on your Pocket PC like never before. Communications, your Office Mobile suite, today's schedule, device status or a display of the current stardate* are all at your command, just one or two stylus taps away.

At last, the usability of LCARS is within reach and in the palm of your hand.

*Pocket LCARS does not calculate stardates as they are based upon warp field and time dilation theories. These technologies are not yet a part of life on Earth. The term "stardate" here refers only to the terran time and date in the time zone for which the device has been configured.

REQUIREMENTS

Hardware:

- Pocket PC 2002 or later.
Note: Your device must support ClearType. This is a known problem on the Toshiba e740 Pocket PC.

Software:

- **Wisbar Advance 2.x or higher**
- **Wisbar Advance Desktop 1.3.x or higher**
Both of these are available from www.lakeridgesoftware.com.
- **TodayAgenda v0.9.50** (recommended)
Freeware written by Marcel Tiewis
Available from <http://www.freewareppc.com/utilities/todayagenda.shtml>

What you get in the Pocket LCARS installation package:

- Pocket LCARS version 40289 (for Wisbar Advance)
- Pocket LCARS version 40289 (for Wisbar Advance Desktop)
- Pocket LCARS version 40289 (for Media Player)
- Pocket LCARS version 40289 Additional Materials (contains additional sounds and fonts)



THE FIRST STEPS

The very first thing you should do is to ensure that you have met the system requirements listed on the right. Assuming that you have met these requirements, I recommend that you install the applications and Pocket LCARS into your Pocket PC's Main Memory. This will ensure that the software will continue to run if you ever have to remove your expansion card.

Every effort has been made to optimize the use of space. This means that we've kept the file sizes small and shared graphics between portrait and landscape modes wherever possible.

HOW TO INSTALL POCKET LCARS

These instructions assume that you have already installed **Wisbar Advance 2.8x** and **Wisbar Advance Desktop 1.3x**.

For ease of installation (and subsequent uninstallation), Pocket LCARS is built into a self-extracting .CAB file that will place all of the files into their appropriate locations on your mobile device. Simply copy the file to your device, then, from your device, launch the file.

SPECIAL NOTES FOR WISBAR ADVANCE 3.x USERS

1. From the Wisbar Advance **Settings** window, tap the **Theme** icon, then tap the **Wisbar Theme** icon.
2. Tap **Menu > Install**.
3. Select **Wisbar 2.x** skins from the dropdown.
4. Now use the dropdown navigator and navigate to *\My Device\Program Files\Lakeridge\Wisbar Advance\Themes\Pocket LCARS*.
5. Select **LCARS_40289** and tap **OK**.
6. Now choose **Pocket LCARS** from the list of themes and tap **Apply**.
7. Select the check boxes for **Taskbar buttons** and **Sound scheme** and tap **OK**.
8. Tap **OK** to close the window.

POST INSTALLTION CONFIGURATION

WISBAR ADVANCE

Start Wisbar Advance if it is not already running. Follow these steps:

1. Tap and hold the **Start** button. When the Tasks menu appears, tap **Settings**. The Settings window of Wisbar Advance will open.
2. Select **Pocket LCARS** as your theme and tap the green checkmark button at the bottom of the screen. This applies the theme, but more configuration is needed.
3. Tap the dropdown at the top right (it currently says **My Theme**) and tap **General Settings**.

System Requirements:

Pocket PC 2002 or higher
Wisbar Advance 2.8x or higher
Wisbar Advance Desktop 1.3x



Illustration 1 on page 3 indicates the recommended settings for use with Pocket LCARS. *Note: The illustration has been modified for clarity.*

4. Tap the dropdown again and select **Start Menu Settings**. Refer to Illustration 2 on page 3 for the recommended selections for **Start Menu Settings**.
5. The recommend settings for **Clock Settings** are that you make the time format **h:mm tt**. If you prefer a 24 hour display (military time), then the time format should be **HH:mm**.
6. For **Button Assignments**, please refer to the table below. Please be advised that these are recommended settings. Please tailor them to suit your individual needs.

Recommended Button Assignments

Dropdown selection	This item is visible	Tap	Hold
Start Menu	YES	Cascading Start Menu	Tasks Panel
Clock	YES	Next Appointment	Tasks Panel
Title	NO	<i>default</i>	<i>default</i>
Notification	YES	Notification	
Volume	YES	Skinnable Volume Bubble	Toggle Mute
Battery/Memory	NO	<i>default</i>	<i>default</i>
Home	NO	<i>default</i>	<i>default</i>
Menu	NO	<i>default</i>	<i>default</i>
Custom 1	NO	<i>default</i>	<i>default</i>
Custom 2	NO	<i>default</i>	<i>default</i>
Connected	YES	Connection	<i>default</i>
Signal Strength	NO	<i>default</i>	<i>default</i>

7. For Button Order, I strongly recommend the following order:
 Clock
 Close
 Notification
 Connection
 Volume

8. Finally, all other default settings should be fine. In Wisbar Advance, select **Plugins** from the dropdown menu and enable **Desktop**. Tap the green check button at the bottom of the screen, then tap **OK** to complete the configuration of Wisbar Advance.




Illustration 1




Illustration 2

WISBAR ADVANCE DESKTOP

Now that Wisbar Advance is running, it will be necessary to tell Wisbar Advance Desktop what theme to use. Tap and hold any blank area (an area that contains no icons) on your screen, then select **Theme Manager**. Tap the **Desktop Theme** icon, then select the **LCARS_portrait_qvga** theme and tap **OK**. Tap **OK** again to exit the Theme Manager.

AGENDA

By default, the first screen to appear will be the Agenda screen. Except for the LCARS graphics, the screen will be blank. You will need to configure which plugins to use. As Wisbar Advance cannot use the built-in Calendar and Tasks plugin, the recommendation here is to install *TodayAgenda* (Freeware written by Marcel Tiews and available from <http://www.tiews.info/index.php?show=&lang=en>).

To set up a Today plugin to be displayed, tap and hold on the screen, then tap **New**, then **Today Plugin**. Select the plugin you want from the list of available Today plugins. You can control how far from the top the plugin should appear. 55 pixels is the optimum position in portrait mode, 40 pixels in landscape mode. Tap **OK** when you're finished.

DEVICE STATUS

There is no configuration necessary for this page. This page will display how much memory your device has and how much it's using, as well as any storage devices you might have (SD and CF cards). The Power Status is also displayed.

LAUNCHER

This page contains a series of shortcuts that are specific to your device and can be created based on the items in your Start Menu or the explicit path to the .exe file.

Pocket LCARS comes pre-configured so that most (if not all) of the apps that came standard on your device will function "right out of the box." You may add to, modify or delete any of these items as you see fit.


Please note: If you plan on rearranging your Start Menu and basing your shortcuts on "Installed Apps," then you should arrange your Start Menu to your liking *before* defining your shortcuts in Wisbar Advance.

To update a shortcut, tap and hold it until a menu appears. Now tap **Properties**. In the resulting window, you will see a dropdown selection called *Tap Action*. You will also see an ellipsis (...) button next to the dropdown. Tap the ellipsis button. You can select the application you want from the list of choices, or you can tap the dropdown and select from your choice of *Control Panel*, *Executables* or *All Files*. Make your selections and tap **OK**. Tap **OK** again to set the properties and return to the desktop.

If your device supports landscape mode, you will need to define the shortcuts in that orientation, as well. Landscape mode is a separate skin set and, therefore, needs to be configured independently of the portrait mode.

MEDIA PLAYER

Select the Pocket LCARS theme from within Media Player. No special configuration is needed. If your device supports landscape mode, you will need to select the Pocket LCARS theme the first time you enter landscape mode.



SOUNDS

A set of sound files is included with your installation package. You can make use of these sounds by tapping **Settings > Personal > Sounds & Notifications**. Now tap the **Notifications** tab. Here are the suggested actions and sound associations:

Event	Play Sound
ActiveSync: Begin sync	None (only because it gets annoying <wink>)
ActiveSync: End sync	None
Beam: Autoreceive	LinkModeActivated
Connection disconnected	LinkCanceled
Connection established	AccessEstablished
Messaging: New e-mail message	PriorityMessage
Messaging: New text message	Hailing
Reminders	Whistle
Wireless network detected	ReestablishingLink

Finally, and in all seriousness, I've had a lot of fun developing this skin set. I hope you have at least as much fun using it!

—Neil Strawbridge
www.PocketLCARS.com



END TRANSMISSION